



# Programming manual

## S-SDK-MSC15

© 2022Gigahertz-Optik GmbH  
All right reserved

<b>1 Information</b>	<b>1</b>
1.1 Disclaimer	1
1.2 Warranty	1
1.3 License	2
1.4 Overview	2
1.5 Contact information of Gigahertz-Optik	2
1.6 System Requirements	2
1.7 Installation	2
1.8 System preparation	3
<b>2 Programming example</b>	<b>4</b>
2.1 C++	4
2.1.1 MSC15Example.cpp	4
2.1.2 MSC15Import.cpp	5
2.1.3 MSC15Import.h	6
2.2 More Examples	6
<b>3 Change History</b>	<b>7</b>
<b>4 Errors and Warnings</b>	<b>8</b>
4.1 Errors	8
4.2 Warnings	9
<b>5 Module Documentation</b>	<b>10</b>
5.1 Information	10
5.2 Standard SDK Methods	11
5.2.1 Detailed Description	11
5.2.2 C++ Example	11
5.2.3 Function Documentation	11
5.2.3.1 GOMDMSC15_setPassword()	11
5.2.3.2 GOMDMSC15_getDLLVersion()	12
5.2.3.3 GOMDMSC15_getHandle()	12
5.2.3.4 GOMDMSC15_releaseHandle()	13
5.2.3.5 GOMDMSC15_getSerialNumber()	13
5.2.3.6 GOMDMSC15_getFirmwareVersion()	13
5.2.3.7 GOMDMSC15_isConnected()	14
5.2.3.8 GOMDMSC15_readStatus()	14
5.2.3.9 GOMDMSC15_getMSC15DeviceType()	15
5.2.3.10 GOMDMSC15_getDetectorType()	15
5.2.3.11 GOMDMSC15_getDetectorSerialNumber()	16
5.2.3.12 GOMDMSC15_getTemperature()	17
5.3 Methods for Device Settings	18
5.3.1 Detailed Description	18
5.3.2 Function Documentation	18

5.3.2.1 GOMDMSC15_setDisplayMode()	18
5.3.2.2 GOMDMSC15_getDisplayMode()	19
5.3.2.3 GOMDMSC15_getAvailableDisplays()	20
5.3.2.4 GOMDMSC15_setDisplayOrientation()	20
5.3.2.5 GOMDMSC15_getDisplayOrientation()	21
5.4 Methods for measurement	22
5.4.1 Detailed Description	22
5.4.2 C++ Example	22
5.4.3 Function Documentation	22
5.4.3.1 GOMDMSC15_measure()	22
5.4.3.2 GOMDMSC15_measureWithManualIntegrationTime()	23
5.4.3.3 GOMDMSC15_measureDarkOffset()	24
5.4.3.4 GOMDMSC15_setMaximalIntegrationTime()	25
5.4.3.5 GOMDMSC15_getMaximalIntegrationTime()	26
5.4.3.6 GOMDMSC15_setDynamicDarkMode()	26
5.4.3.7 GOMDMSC15_isOffsetInvalid()	27
5.4.3.8 GOMDMSC15_getOffsetTime()	27
5.4.3.9 GOMDMSC15_measurePulse()	28
5.4.3.10 GOMDMSC15_dequeuePulse()	29
5.4.3.11 GOMDMSC15_abortPulse()	29
5.5 Methods for spectral measurement settings	31
5.5.1 Detailed Description	31
5.5.2 C++ Example	31
5.5.3 Function Documentation	31
5.5.3.1 GOMDMSC15_getLastIntegrationTime()	31
5.5.3.2 GOMDMSC15_getWLBorders()	32
5.5.3.3 GOMDMSC15_getWLMapping()	32
5.5.3.4 GOMDMSC15_getSpectralDataByPixel()	33
5.5.3.5 GOMDMSC15_getSpectralData()	33
5.5.3.6 GOMDMSC15_getPeakWL()	34
5.5.3.7 GOMDMSC15_getCentreWL()	34
5.5.3.8 GOMDMSC15_getCentroidWL()	34
5.5.3.9 GOMDMSC15_getFWHM()	35
5.6 Methods for integral measurement settings	36
5.6.1 Detailed Description	36
5.6.2 C++ Example	36
5.6.3 Function Documentation	36
5.6.3.1 GOMDMSC15_getPhotopic()	36
5.6.3.2 GOMDMSC15_getScotopic()	37
5.6.3.3 GOMDMSC15_getSPRatio()	37
5.6.3.4 GOMDMSC15_getRadiometricUnit()	37
5.6.3.5 GOMDMSC15_getRadiometricValue()	38

5.6.3.6 GOMDMSC15_getPAR()	38
5.6.3.7 GOMDMSC15_getBilirubinIEC()	39
5.6.3.8 GOMDMSC15_getBilirubinAAP()	39
5.6.3.9 GOMDMSC15_getBilirubinAAP2004()	40
5.6.3.10 GOMDMSC15_getBilirubinNatus()	40
5.6.3.11 GOMDMSC15_getMelanopic()	40
5.7 Methods for color measurement	42
5.7.1 Detailed Description	42
5.7.2 C++ Example	42
5.7.3 Function Documentation	42
5.7.3.1 GOMDMSC15_getColor()	42
5.7.3.2 GOMDMSC15_getColorCIE1931()	43
5.7.3.3 GOMDMSC15_getColorCIE1976()	43
5.7.3.4 GOMDMSC15_getCRI()	44
5.7.3.5 GOMDMSC15_getCCT()	44
5.7.3.6 GOMDMSC15_getDomWL()	45
5.7.3.7 GOMDMSC15_getCompWL()	45
5.7.3.8 GOMDMSC15_getDeltauv()	46
5.7.3.9 GOMDMSC15_getPurity()	46
5.7.3.10 GOMDMSC15_getTM3018()	46
5.7.3.11 GOMDMSC15_getTM3018RfByHue()	47
5.8 Load stored Measurements from Device	48
5.8.1 Detailed Description	48
5.8.2 Function Documentation	48
5.8.2.1 GOMDMSC15_loggerReadDate()	48
5.8.2.2 GOMDMSC15_loggerLoadMeasurement()	49
5.8.2.3 GOMDMSC15_loggerDeleteMeasurement()	49
5.8.2.4 GOMDMSC15_loggerSetRTC()	50
5.8.2.5 GOMDMSC15_loggerGetRTC()	50
5.9 Methods only for MSC15-W-devices	52
5.9.1 Detailed Description	52
5.9.2 Function Documentation	52
5.9.2.1 GOMDMSC15_setUserWLRRangeBorders()	52
5.9.2.2 GOMDMSC15_setUserWLRRangeBoardsers()	53
5.9.2.3 GOMDMSC15_setUserWLRRangeBordersToFactory()	53
5.9.2.4 GOMDMSC15_getUserWLRRangeBorders()	54
5.9.2.5 GOMDMSC15_getUserWLRRangeBoardsers()	54
5.9.2.6 GOMDMSC15_getSelectedUserWLRRange()	54
5.9.2.7 GOMDMSC15_setSelectedUserWLRRange()	55
5.9.2.8 GOMDMSC15_getUserWLRRangeActive()	55
5.9.2.9 GOMDMSC15_getUserWLRRangeModifiable()	56
5.9.2.10 GOMDMSC15_getUserWLRRangeRadiometric()	57

---

5.9.2.11 GOMDMSC15_setAppertureSize() . . . . .	57
5.9.2.12 GOMDMSC15_getAppertureSize() . . . . .	58
5.9.2.13 GOMDMSC15_getAppertureSizeBorders() . . . . .	58
5.9.2.14 GOMDMSC15_setAppertureIndex() . . . . .	59
5.9.2.15 GOMDMSC15_getAppertureIndex() . . . . .	60
5.9.2.16 GOMDMSC15_setUserCorrectionFactor() . . . . .	60
5.9.2.17 GOMDMSC15_getUserCorrectionFactor() . . . . .	61
5.9.2.18 GOMDMSC15_setUserCorrectionFactorLocked() . . . . .	61
5.9.2.19 GOMDMSC15_getUserCorrectionFactorLocked() . . . . .	62

# Kapitel 1

## Information



Please read this documentation and the disclaimer carefully before using the software.

**By installing and using the software, you explicitly and fully acknowledge and agree to this.**

Gigahertz-Optik GmbH reserves the right to make changes to this manual without prior notice.

### 1.1 Disclaimer

This software was developed with utmost care and thoroughly tested on different computers. No errors were noted for the approved product versions. However, it cannot be guaranteed that the software will work perfectly on all types of computers. Completely error-free software is not possible with the current technology level.

Gigahertz-Optik GmbH is not liable if the software does not perfectly fulfill your desired purpose or if it is incompatible with other software on your computer. You are therefore solely responsible for the choice, installation and use as well as for the intended results.

With the exception of damages caused deliberately, Gigahertz-Optik GmbH is not liable for any damages caused by the use or inability to use the software. This also exclusively applies for loss of business profits, business interruptions, loss of business information or any other economic losses, even if Gigahertz-Optik GmbH had been previously advised of the possibility of such damage. The enclosed documentation/help of the software is with no claim of accuracy or completeness.

### 1.2 Warranty

Gigahertz-Optik GmbH guarantees the delivery of all functions listed in the product description. Any available delivery media are free of any material defects.

We have taken all the necessary and possible steps that are required to keep this software free of viruses, spyware, the so-called "back door entrances" or other harmful code. We do not collect any information about you or your data. We will not deliberately limit you from using the functions of this software or access to your data. This agreement supersedes any non-contractual assurances that we may have explained to you. Any modification to this agreement must be confirmed in writing by both parties.

## 1.3 License

A license for the full version allows you to use the product on only one workstation. Each concurrent use on another workstation requires an additional product license. The distribution of the product and documentation is prohibited. You are authorized to make a copy of this product for your backup purposes. You may pass on your own software that you have developed using this development package together with the required DLLs for this development package to third parties.

## 1.4 Overview

This development package provides you with all the tools required (no compiler or integrated software development environments) to directly control a MSC15 and CSS device type series measurement device from Gigahertz-Optik using C/C++. This is primarily with regards to the communication and control libraries for your MSC15 and CSS device type.

In order to use these libraries, you need a programming environment such as Microsoft Visual Studio, Embarcadero C++ builder, etc.

## 1.5 Contact information of Gigahertz-Optik

Gigahertz Optik GmbH	Gigahertz-Optik Inc
An der Kälberweide 12 D-82299 Türkenfeld Germany Tel.: +49 8193 93700-0 Fax: +49 8193 93700-50 Email: <a href="mailto:info@gigahertz-optik.de">info@gigahertz-optik.de</a> Homepage: <a href="http://www.gigahertz-optik.de">http://www.gigahertz-optik.de</a>	110 Haverhill Road Amesbury MA 01913 USA Tel: + 978 462 1818 Fax: + 978 462 3677 Email: <a href="mailto:b.angelo@gigahertz-optik.com">b.angelo@gigahertz-optik.com</a> Homepage: <a href="https://www.gigahertz-optik.com">https://www.gigahertz-optik.com</a>

## 1.6 System Requirements

To use the S-SDK MSC15 and CSS device type you have to consider the following points:

- Minimum disk space – approx. 10MB
- Operation system: MS Windows XP, MS Windows 7 (32bit/64bit), MS Windows 10 (32bit/64bit)
- C/C++ development environment such as MS Visual Studio, Embarcadero C++ Builder, etc. when programming with C/C++
- free USB port

## 1.7 Installation

Follow the steps below to install the MSC15 and CSS device type-SDK from the product CD:

- Read this documentation before you begin the installation

- Close all other applications before installing
- Insert the CD in your CD drive or unpack the supplied ZIP file.
- Copy the Gigahertz-Optik folder from the CD or ZIP file to a location of your choice. If you have already got other development packages from Gigahertz-Optik installed, it is recommended to use the same installation path in order to avoid possible conflicts.
- Add the folder "install dir/Gigahertz-Optik/runtime" to your system path. "install dir" hereby corresponds to the base path you added in step 4 above. If you have already got other development packages from Gigahertz-Optik installed, step 5 might not be necessary.

## 1.8 System preparation

Connect the MSC15 and CSS device type to your computer. The required drivers are standard windows drivers and will be installed automatically.

The SDK is password protected! Each programm created with this SDK has to call the function setPassword() before any other function can be called.



## Kapitel 2

# Programming example

Example - How to import DLL in your application

### Note

The method descriptions (Module) provide examples of how to use the SDK methods.

## 2.1 C++

As we don't deliver import libraries for different development environments you have to use run-time dynamic linking to be able to use all methods provided by dll.

Following is an C++ example of how to import and use methods from DLL. The example does not include all available methods. The use of the handles is encapsulated in the class. The example searches and initializes a MSC15 and CSS device type, performs a measurement and then records the results in the console.

At the end, all MSC15 and CSS device type-resources are released again.

### 2.1.1 MSC15Example.cpp

```
#include "MSC15Import.h"
#include <iostream>
int main(int argc, char* argv[])
{
    MSC15Import msc15;
    //search for a MSC15 device
    //first you have to replace the right password in the msc15Import.cpp
    int error = msc15.init("MSC15_0");
};
    if (error == 0)
    {
        //set measurement mode and start a new measurement
        error = msc15.measure();
        //if no error occurred read the integral values
        if (error == 0)
        {
            double value;
            msc15.getPhotopic(&value);
            std::cout << "E(V):"
            << value << std::endl;
            msc15.getCCT(&value);
            std::cout << "CCT:"
            << value << std::endl;
        }
        else
        {
            std::cout << "Error occurred:"
            << error << std::endl;
        }
        msc15.close();
    }
```

```

    }
    else
    {
        std::cout << "error occured:
    << error << std::endl;
    }
    system("PAUSE
);
}

```

## 2.1.2 MSC15Import.cpp

```

#include "MSC15Import.h
MSC15Import::MSC15Import()
{
    hDLLGOMSC15 = NULL;
    handle = -1;
}
MSC15Import:: MSC15Import()
{
}
int __stdcall MSC15Import::init(char* deviceName)
{
    int l_rc = 0;
    if (handle > 0)
        close();
    if (GetProcAddresses(&hDLLGOMSC15, "GOMDMSC15.dll
, 6,
        &GOMDMSC15_setPassword, "GOMDMSC15_setPassword
,
        &GOMDMSC15_getHandle, "GOMDMSC15_getHandle
,
        &GOMDMSC15_releaseHandle, "GOMDMSC15_releaseHandle
,
        &GOMDMSC15_measure, "GOMDMSC15_measure
,
        &GOMDMSC15_getCCT, "GOMDMSC15_getCCT
,
        &GOMDMSC15_getPhotopic, "GOMDMSC15_getPhotopic
    ))
    {
        try {
            l_rc = GOMDMSC15_setPassword("passw
); //replace passw with the right password
            if (l_rc == 0)
                l_rc = GOMDMSC15_getHandle(deviceName, &handle);
            if (handle > 0)
                std::cout << "Initialisation sucessfull
    << std::endl;
        }
        catch (...) {
            l_rc = -1;
        }
    }
    else {
        l_rc = -1;
    }
    return l_rc;
}
int __stdcall MSC15Import::measure()
{
    int l_rc = GOMDMSC15_measure(handle);
    return l_rc;
}
int __stdcall MSC15Import::getPhotopic(double* value)
{
    int l_rc = GOMDMSC15_getPhotopic(handle, value);
    return l_rc;
}
int __stdcall MSC15Import::getCCT(double* value)
{
    int l_rc = GOMDMSC15_getCCT(handle, value);
    return l_rc;
}
int __stdcall MSC15Import::close()
{
    int l_rc = GOMDMSC15_releaseHandle(handle);
    handle = -1;
    return l_rc;
}
bool __stdcall MSC15Import::GetProcAddresses(HINSTANCE *p_hLibrary,
const char* p_dllName, INT p_count, ...)
{
    va_list l_va;

```

```

va_start(l_va, p_count);
if ((*p_hLibrary = LoadLibrary(p_dllName)) != NULL)
{
    FARPROC* l_procFunction = NULL;
    char* l_funcName = NULL;
    int l_idxCount = 0;
    while (l_idxCount < p_count)
    {
        l_procFunction = va_arg(l_va, FARPROC*);
        l_funcName = va_arg(l_va, LPSTR);
        if ((*l_procFunction =
            GetProcAddress(*p_hLibrary, l_funcName)) == NULL)
        {
            l_procFunction = NULL;
            return false;
        }
        l_idxCount++;
    }
}
else
{
    va_end(l_va);
    return false;
}
va_end(l_va);
return true;
}

```

### 2.1.3 MSC15Import.h

```

#ifndef MSC15ImportH
#define MSC15ImportH
#include <Windows.h>
#include <stdio.h>
#include <iostream>
class MSC15Import
{
public:
    MSC15Import();
    virtual MSC15Import();
    int __stdcall init(char* deviceName);
    int __stdcall close();
    int __stdcall getPhotopic(double* value);
    int __stdcall getCCT(double* value);
    int __stdcall measure();
private:
    int handle;
    HINSTANCE hDLLGOMSC15;
    bool __stdcall getProcAddresses(HINSTANCE *p_hLibrary, const char* p_dllName, int p_count, ...);
    int(__stdcall *GOMDMSC15_setPassword)(char* value);
    int(__stdcall *GOMDMSC15_getHandle)(char* device, int* handle);
    int(__stdcall *GOMDMSC15_releaseHandle)(int handle);
    int(__stdcall *GOMDMSC15_measure)(int handle);
    int(__stdcall *GOMDMSC15_getCCT)(int handle, double* value);
    int(__stdcall *GOMDMSC15_getPhotopic)(int handle, double* value);
};
#endif

```

## 2.2 More Examples

Further examples for integrating DLL's, can be found in the installation directory of the SDK.

## Kapitel 3

# Change History

A list of all modifications of the S-SDK-MSC15 follows:

- **V2016.1:** New: Release of the SDK
- **V2017.1:** New: Support for MSC15-W devices/ New: TM-30-15/ Update: bilirubin and Melanopic to the new standards.
- **V2017.2:** New: Range in pixel-based steps/ Update: adjusted maximum measurement time of the pulse measurement on the sample rate
- **V2018.1:** New: Support for CSS-45
- **V2019.1:** New: Load measurement data from internal logger/ New: Wavelength Correction
- **V2019.2:** Bugfix: color calculation
- **V2019.3:** New: Support for CSS-45-D, Bugfix: RS485 Communication
- **V2019.4:** Update: TM-30-15 to TM-30-18, Bugfix: Functionnames in Interface
- **V2019.5:** New: GOMDMSC15\_measureWithManualIntegrationTime(), Bugfix: Error with firmware > 1.45,
- **V2019.6:** Bugfix: GOMDMSC15\_getLastIntegrationTime(), New: GOMDMSC15\_getTemperature()
- **V2019.7:** Update: Calculation of measurement values will be done in DLL (faster)
- **V2020.1:** Update: Melanopsin after CIE S026
- **V2020.2:** New: Support for MSC15-Bili V01
- **V2020.3:** Update: User WL-Ranges of MSC15-W
- **V2020.4:** Update: Measurement error: no/low signal
- **V2021.1:** Update: set RS485 baudrate of CSS-45/ Bugfix: internal Logger and RTC
- **V2021.2:** New: complementary wavelength/ Bugfix: dominant wavelength and CRI calculation
- **V2022.1:** Bugfix: Color Rendering
- **V2022.2:** New: Support CSS-45-Bili
- **V2022.3:** New: GOMDMSC15\_setMaximalIntegrationTime()

# Kapitel 4

## Errors and Warnings

A list of errors and warnings follows:

### 4.1 Errors

- -500: Communication Error
- -25000: Communication Problems
- -25001: Setup file invalid for device
- -25002: Setup file could not be opened
- -25004: Not a valid handle
- -25005: Communication channel cannot be initialized
- -25006: Too low Firmware Version
- -25007: Problem sending data
- -25008: Problem with data receive
- -25009: device sends an unspecified error
- -25012: Units do not match
- -25013: Error pixel correction eeprom
- -25014: Error main data eeprom
- -25015: Error color data eeprom
- -25016: Error correction factor data eeprom
- -25017: Error dark value eeprom
- -25018: Error calibration factor eeprom
- -25019: Error offset eeprom
- -25020: Too much ambient light
- -25021: measurement aborted
- -25024: Error userdata eeprom

- -25025: The spectral unit reported weak signal
- -25030: Not available
- -25031: Wrong device type, method not valid
- -25032: It was handed over to a wrong password
- -25041: Device Type CSS-D without detector not valid for SDK
- -25100: Value out of range

## 4.2 Warnings

- 25003: file not found: there were previously saved any default data. Therefore, no default file exists
- 25010: Battery low
- 25022: unstable signal
- 25023: the spectral unit reports an "overload"

## Kapitel 5

# Module Documentation

### 5.1 Information

Common information regarding the functions of the GOMDMS15 DLL.

All the methods described here can be applied to every MSC15 and CSS device type. You can see the supported device variants in the function `GOMDMS15_getMSC15DeviceType()`. Certain differences in the application can arise depending on the configuration, calibration and features of your measurement device. For instance, some methods may fail to provide any results for certain device configurations.

Each method provides a return value. Return value "0" means error-free execution of the method. Values less than "0" indicate the occurrence of an error. Values larger than "0" should be regarded as warnings.

A list of all return values is include in the documentation.



## 5.2 Standard SDK Methods

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_setPassword (char \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getDLLVersion (char \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getHandle (char \*deviceName, int \*handle)
- GODLL int GOFUNCDESC GOMDMSC15\_releaseHandle (int handle)
- GODLL int GOFUNCDESC GOMDMSC15\_getSerialNumber (int handle, char \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getFirmwareVersion (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_isConnected (int handle, bool \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_readStatus (int handle, int \*status)
- GODLL int GOFUNCDESC GOMDMSC15\_getMSC15DeviceType (int handle, int \*type)
- GODLL int GOFUNCDESC GOMDMSC15\_getDetectorType (int handle, int \*type)
- GODLL int GOFUNCDESC GOMDMSC15\_getDetectorSerialNumber (int handle, char \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getTemperature (int handle, double \*value)

### 5.2.1 Detailed Description

Methods for handling the SDK and device.

### 5.2.2 C++ Example

This example describes the initialization of your device. This is the default structure of initialization:

```
GOMDMSC15_setPassword("Your password");
int handle;
int l_rc = GOMDMSC15_getHandle("MSC15_0", &handle); // initialization of device
if (handle > 0 )
{
    // do something
}
GOMDMSC15_releaseHandle(handle); // re-initialization of device
```

### 5.2.3 Function Documentation

#### 5.2.3.1 GOMDMSC15\_setPassword()

```
GODLL int GOFUNCDESC GOMDMSC15_setPassword (
    char * value )
```

This method must be called before any other to unlock the use of the SDK. The activation takes place on several levels.

- Layer1: Using the SDK in general
- Layer2: All elements of the 1st level plus the storage of calibrations in the user-specific memory area  
The passwords are you ever received from the Gigahertz-Optik GmbH separately.



**Parameters**

in	<i>value</i>	Null-terminated string that contains the password.
----	--------------	--

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.2 GOMDMSC15\_getDLLVersion()**

```
GODLL int GOFUNCDESC GOMDMSC15_getDLLVersion (
    char * value )
```

Returns the version number of this DLL.

**Parameters**

out	<i>value</i>	Null-terminated string; contains by return the version number, minimum size: 10 bytes
-----	--------------	---

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.3 GOMDMSC15\_getHandle()**

```
GODLL int GOFUNCDESC GOMDMSC15_getHandle (
    char * deviceName,
    int * handle )
```

After activation of the SDK must be called next, to initialize the MSC15 principle this method. The parameter "handle" contains a unique sequence number for instantiated instrument that needs to be passed as the first parameter when all other methods.

**Parameters**

in	<i>deviceName</i>	Null-terminated string that identifies the desired device to be initialized. The string is always the following structure: "MSC15_\ <serial\&gt;" "css45_0_adr147"="" "css45_\<serial\&gt;".="" "msc15_0".="" "msc15_5678"="" &amp;handle)="" &lt;serial&gt;="" ("msc15_0",="" 147.<="" 5678.="" a="" add="" address="" adrxxx="" another="" as="" call="" can="" connected="" conneted="" css-45="" css45,="" device="" device.="" e.g.="" first="" for="" gethandle="" handle="" if="" initialization="" initialize="" initialized="" initialized.="" instrument.="" is="" msc15="" next="" not="" number="" of="" on="" or="" parameter="" placeholder="" possibility="" provided="" registered="" released.="" returns="" rs-485="" serial="" specify="" string="" td="" that="" the="" thus,="" to="" transfer="" via="" was="" windows="" with="" you=""></serial\&gt;">
out	<i>handle</i>	Pointer to an integer value; This value includes to return a handle > 0 if the initialization was successful, otherwise 0.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.4 GOMDMSC15\_releaseHandle()**

```
GODLL int GOFUNCDESC GOMDMSC15_releaseHandle (
    int handle )
```

This method must be called at the end, to release the resources / memory occupied by MSC15/CSS-45 again.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	---------------	--

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.5 GOMDMSC15\_getSerialNumber()**

```
GODLL int GOFUNCDESC GOMDMSC15_getSerialNumber (
    int handle,
    char * value )
```

Returns the serial number of the connected device. If you use a CSS-D + CSS-45 see also GOMDMSC15\_getDetectorSerialNumber().

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Null-terminated string; contains by return the serial number of the device, minimum size: 10 bytes

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.6 GOMDMSC15\_getFirmwareVersion()**

```
GODLL int GOFUNCDESC GOMDMSC15_getFirmwareVersion (
    int handle,
    double * value )
```

Returns the firmware version of the direct connected device with PC.  
Example: CSS-D and CSS-45, returns the FW-version of CSS-D

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Null-terminated string; contains by return, the firmware version, minimum size: 10 bytes

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.7 GOMDMSC15\_isConnected()**

```
GODLL int GOFUNCDESC GOMDMSC15_isConnected (
    int handle,
    bool * value )
```

Gets whether the device is still connected to the current handle.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Boolean; contains, if the device is connected: <ul style="list-style-type: none"><li>• true: MSC15 and CSS device type is connected</li><li>• false: MSC15 and CSS device type is not connected</li></ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.8 GOMDMSC15\_readStatus()**

```
GODLL int GOFUNCDESC GOMDMSC15_readStatus (
    int handle,
    int * status )
```

Gets the current device status of MSC15/CSS-45 (see Errors and Warnings).

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>status</i>	Integer; at values equal to "0" see return value table (Errors and Warnings).

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.9 GOMDMSC15\_getMSC15DeviceType()**

```
GODLL int GOFUNCDESC GOMDMSC15_getMSC15DeviceType (
    int handle,
    int * type )
```

Returns the type of the connected MSC15 and CSS device type-device.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>type</i>	Integer; the device type. <ul style="list-style-type: none"> <li>• 0: undefined</li> <li>• 1: MSC15</li> <li>• 2: MSC15-W</li> <li>• 3: LVMH-spectralux100</li> <li>• 4: CSS-45</li> <li>• 5: CSS-45-WT</li> <li>• 6: CSS - D</li> <li>• 7: CSS - 45 - HI</li> <li>• 8: MSC15 - Bili</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.10 GOMDMSC15\_getDetectorType()**

```
GODLL int GOFUNCDESC GOMDMSC15_getDetectorType (
    int handle,
    int * type )
```

**Note**

This function can be used with the following device types: **CSS-D**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Checks if an external detector (e.g. CSS-45, CSS-45-HI, CSS-45-WT, etc.) is connected to the CSS-D and returns the device type of the connected device.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>type</i>	Integer value; indicates the device type of the connected detector. The number corresponds to the function GOMDMSC15_getMSC15DeviceType(). E.g. type = 7 = CSS-45-HI

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.2.3.11 GOMDMSC15\_getDetectorSerialNumber()**

```
GODLL int GOFUNCDESC GOMDMSC15_getDetectorSerialNumber (
    int handle,
    char * value )
```

**Note**

This function can be used with the following device types: **CSS-D**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Returns the serial number of the connected detector device. Example CSS-D + CSS-45.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Null-terminated string; contains by return the serial number of the detector device, minimum size: 10 bytes

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

### 5.2.3.12 GOMDMSC15\_getTemperature()

```
GODLL int GOFUNCDESC GOMDMSC15_getTemperature (
    int handle,
    double * value )
```

Reads the current board temperature of the device. This can be used for relative temperature measurements.

MSC15: Circuit board temperature MSC-15

CSS-45: PCB temperature CSS-45

CSS-D + CSS-45: PCB temperature CSS-45

--> Sensor always reads the temperature of the sensor.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Double value, includes the temperature.

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

## 5.3 Methods for Device Settings

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_setDisplayMode (int handle, int mode)
- GODLL int GOFUNCDESC GOMDMSC15\_getDisplayMode (int handle, int \*mode)
- GODLL int GOFUNCDESC GOMDMSC15\_getAvailableDisplays (int handle, int \*mode)
- GODLL int GOFUNCDESC GOMDMSC15\_setDisplayOrientation (int handle, bool rotated)
- GODLL int GOFUNCDESC GOMDMSC15\_getDisplayOrientation (int handle, bool \*rotated)

### 5.3.1 Detailed Description

Methods to call and change device settings.

### 5.3.2 Function Documentation

#### 5.3.2.1 GOMDMSC15\_setDisplayMode()

```
GODLL int GOFUNCDESC GOMDMSC15_setDisplayMode (
    int handle,
    int mode )
```

#### Note

This function can be used with the following device types: **MSC15, MSC15-W, MSC15-Bili, CSS-45, CSS-45-WT, CSS-45-HI, CSS-D + Detector**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This function activated/deactivates certain displays a the MSC15 and CSS device type-device. CSS-45 has no display, but the display settings are stored in combination with a display unit (CSS-D) in the CSS-45. The CSS-D serves only as a pure display element.

Attention: Not all displays can be activated. To check the available displays for your device call GOMDMSC15\_getAvailableDisplays().

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	---------------	--

## Parameters

<i>in</i>	<i>mode</i>	<p>Integer value is interpreted bit-wise:</p> <ul style="list-style-type: none"> <li>• Bit 0: Graphics / E / CT (only MSC15)</li> <li>• Bit 1: CRI (only MSC15)</li> <li>• Bit 2: E / CT (only MSC15)</li> <li>• Bit 3: ES / EP (only MSC15)</li> <li>• Bit 4: Graphics / PAR (only MSC15)</li> <li>• Bit 5: Graphics / bilirubin (outdated)</li> <li>• Bit 6: Melanopic / brightness factor (outdated)</li> <li>• Bit 7: Graphics / E / CT Irradiance (only MSC15)</li> <li>• Bit 8: free</li> <li>• Bit 9: Radiant power for up to 8 wavelength ranges (only MSC15-W)</li> <li>• Bit 10: Irradiance for up to 8 wavelength ranges (only MSC15-W)</li> <li>• Bit 11: CIE1931 color triangle (only MSC15)</li> <li>• Bit 12: Graphics / Radiant Power / Irradiance (only MSC15-W)</li> <li>• Bit 13: Graphics / Irradiance (only MSC15-W)</li> <li>• Bit 14: Meter Only (only MSC15-W)</li> <li>• Bit 15: Graphics / IEC bilirubin (only MSC15)</li> <li>• Bit 16: Graphics / bilirubin AAP (only MSC15)</li> <li>• Bit 17: Melanopic (only MSC15)</li> <li>• Bit 18: TM-30-18 (fw <math>\geq 1.48</math>) / TM-30-15 (fw <math>&lt; 1.48</math>)(only MSC15)</li> <li>• Bit 19: Graphics / Bilirubin BLUE LED (only MSC15-Bili)</li> <li>• Bit 20: Graphics / Bilirubin AAP(2004) (only MSC15-Bili)</li> <li>• Bit 21: Bilirubin IEC (only MSC15-Bili)</li> <li>• Bit 22: Bilirubin AAP(2011) (only MSC15-Bili)</li> <li>• Bit 23: Bilirubin BLUE LED (only MSC15-Bili)</li> <li>• Bit 24: Bilirubin AAP(2004) (only MSC15-Bili)</li> </ul>
-----------	-------------	--

## Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

## 5.3.2.2 GOMDMSC15\_getDisplayMode()

```
GODLL int GOFUNCDESC GOMDMSC15_getDisplayMode (
    int handle,
    int * mode )
```



/note MSC15, MSC15-W, MSC15-Bili, CSS-45, CSS-45-WT, CSS-45-HI, CSS-D + Detector

This method returns the active display function.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>mode</i>	Pointer to integer value, is interpreted bit-wise, see setDisplayMode().

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.3.2.3 GOMDMSC15\_getAvailableDisplays()

```
GODLL int GOFUNCDESC GOMDMSC15_getAvailableDisplays (
    int handle,
    int * mode )
```

#### Note

This function can be used with the following device types: **MSC15, MSC15-W, MSC15-Bili, CSS-45, CSS-45-WT, CSS-45-HI, CSS-D + Detector**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This method returns the available display function.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>mode</i>	Pointer to integer value, is interpreted bit-wise, see setDisplayMode().

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.3.2.4 GOMDMSC15\_setDisplayOrientation()

```
GODLL int GOFUNCDESC GOMDMSC15_setDisplayOrientation (
    int handle,
    bool rotated )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This function sets the orientation of the device display.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>rotated</i>	Boolean value: <ul style="list-style-type: none"> <li>• true: Display is rotated by 180°</li> <li>• false: Display is not rotated by 180°</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.3.2.5 GOMDMSC15\_getDisplayOrientation()**

```
GODLL int GOFUNCDESC GOMDMSC15_getDisplayOrientation (
    int handle,
    bool * rotated )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This function reads back the orientation of the device display.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>rotated</i>	Pointer to Boolean value, the display is upside down: <ul style="list-style-type: none"> <li>• true: Display is rotated by 180°</li> <li>• false: Display is not rotated by 180</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

## 5.4 Methods for measurement

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_measure (int handle)
- GODLL int GOFUNCDESC GOMDMSC15\_measureWithManualIntegrationTime (int handle, int index)
- GODLL int GOFUNCDESC GOMDMSC15\_measureDarkOffset (int handle)
- GODLL int GOFUNCDESC GOMDMSC15\_setMaximalIntegrationTime (int handle, int index)
- GODLL int GOFUNCDESC GOMDMSC15\_getMaximalIntegrationTime (int handle, int \*index)
- GODLL int GOFUNCDESC GOMDMSC15\_setDynamicDarkMode (int handle, int mode)
- GODLL int GOFUNCDESC GOMDMSC15\_isOffsetInvalid (int handle, bool \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getOffsetTime (int handle, int \*timeInMs)
- GODLL int GOFUNCDESC GOMDMSC15\_measurePulse (int handle, double pulseTime, double samplingRate)
- GODLL int GOFUNCDESC GOMDMSC15\_dequeuePulse (int handle, double \*timer, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_abortPulse (int handle)

### 5.4.1 Detailed Description

Methods to prepare and perform a measurement.

### 5.4.2 C++ Example

This example shows a measurement with the MSC15 and CSS device type-device.

```
GOMDMSC15_getHandle (NULL, &handle);      //initialization of device
GOMDMSC15_measure (handle);               //start measure
//do something
GOMDMSC15_releaseHandle (handle);         //re-initialization of device
```

### 5.4.3 Function Documentation

#### 5.4.3.1 GOMDMSC15\_measure()

```
GODLL int GOFUNCDESC GOMDMSC15_measure (
    int handle )
```

This method triggers the measurement. The measured values are stored in the device and can be accessed with the functions

- Methods for spectral measurement settings
- Methods for color measurement
- ...

**Parameters**

in	<i>handle</i>	Integer value $> 0$ for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	---------------	--

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.2 GOMDMSC15\_measureWithManualIntegrationTime()**

```
GODLL int GOFUNCDESC GOMDMSC15_measureWithManualIntegrationTime (
    int handle,
    int index )
```

This method triggers the measurement with a manual integration time. The measured values are stored in the device and can be accessed with the functions

- Methods for spectral measurement settings
- Methods for color measurement
- ...

**Parameters**

in	<i>handle</i>	Integer value $> 0$ for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	---------------	--

## Parameters

in	index	integer value connected to integration time:
		<ul style="list-style-type: none"> <li>• 0: integration time: 0.000012 s</li> <li>• 1: integration time: 0.00002 s</li> <li>• 2: integration time: 0.00004 s</li> <li>• 3: integration time: 0.00008 s</li> <li>• 4: integration time: 0.00016 s</li> <li>• 5: integration time: 0.00032 s</li> <li>• 6: integration time: 0.00064 s</li> <li>• 7: integration time: 0.00125 s</li> <li>• 8: integration time: 0.0025 s</li> <li>• 9: integration time: 0.005 s</li> <li>• 10: integration time: 0.01 s</li> <li>• 11: integration time: 0.02 s</li> <li>• 12: integration time: 0.04 s</li> <li>• 13: integration time: 0.08 s</li> <li>• 14: integration time: 0.16 s</li> <li>• 15: integration time: 0.32 s</li> <li>• 16: integration time: 0.64 s</li> <li>• 17: integration time: 1.28 s</li> <li>• 18: integration time: 2.56 s</li> </ul>

## Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

## 5.4.3.3 GOMDMSC15\_measureDarkOffset()

```
GODLL int GOFUNCDESC GOMDMSC15_measureDarkOffset (
    int handle )
```

This method starts the measurement of the dark offset. On a MSC15 device the shutter must be closed and reopened manually after the offset measurement. With the CSS-45 the shutter will be closed and opened automatically. The measured offset is automatically deducted from the (light) measurements.

## Parameters

in	handle	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	--------	--

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.4 GOMDMSC15\_setMaximalIntegrationTime()**

```
GODLL int GOFUNCDESC GOMDMSC15_setMaximalIntegrationTime (
    int handle,
    int index )
```

This method sets the maximal integration time used by the function GOMDMSC15\_measure() .

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	integer value connected to integration time: <ul style="list-style-type: none"> <li>• 0: integration time: 0.000012 s</li> <li>• 1: integration time: 0.00002 s</li> <li>• 2: integration time: 0.00004 s</li> <li>• 3: integration time: 0.00008 s</li> <li>• 4: integration time: 0.00016 s</li> <li>• 5: integration time: 0.00032 s</li> <li>• 6: integration time: 0.00064 s</li> <li>• 7: integration time: 0.00125 s</li> <li>• 8: integration time: 0.0025 s</li> <li>• 9: integration time: 0.005 s</li> <li>• 10: integration time: 0.01 s</li> <li>• 11: integration time: 0.02 s</li> <li>• 12: integration time: 0.04 s</li> <li>• 13: integration time: 0.08 s</li> <li>• 14: integration time: 0.16 s</li> <li>• 15: integration time: 0.32 s</li> <li>• 16: integration time: 0.64 s</li> <li>• 17: integration time: 1.28 s</li> <li>• 18: integration time: 2.56 s</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.5 GOMDMSC15\_getMaximalIntegrationTime()**

```
GODLL int GOFUNCDESC GOMDMSC15_getMaximalIntegrationTime (
    int handle,
    int * index )
```

This method reads the maximal integration time, used by the function GOMDMSC15\_measure() .

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	pointer to integer value connected to integration time (see GOMDMSC15_setMaximalIntegrationTime() )

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.6 GOMDMSC15\_setDynamicDarkMode()**

```
GODLL int GOFUNCDESC GOMDMSC15_setDynamicDarkMode (
    int handle,
    int mode )
```

**Note**

This function can be used with the following device types: **CSS-45, CSS-45-HI, CSS-45-WT**  
The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This method is only available for CSS devices.

When activated (mode = 1) after each measurement a dark measurement with the same integration time will be done and used for calculation.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>mode</i>	integer value: <ul style="list-style-type: none"> <li>• 0: dynamic dark mode gets deactivated</li> <li>• 1: dynamic dark mode gets activated</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.7 GOMDMSC15\_isOffsetInvalid()**

```
GODLL int GOFUNCDESC GOMDMSC15_isOffsetInvalid (
    int handle,
    bool * value )
```

**Note**

This function can be used with the following device types: **CSS-45, CSS-45-HI, CSS-45-WT**  
The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

The method specifies whether the dark current trigger the device is still valid. If not, it must be re-measured by the GOMDMSC15\_measureDarkOffset() method.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Boolean value: <ul style="list-style-type: none"> <li>• true: Dark deduction is invalid</li> <li>• false: Dark deduction is not invalid</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.8 GOMDMSC15\_getOffsetTime()**

```
GODLL int GOFUNCDESC GOMDMSC15_getOffsetTime (
    int handle,
    int * timeInMs )
```

**Note**

This function can be used with the following device types: **CSS-45, CSS-45-HI, CSS-45-WT**  
The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Specifies the time required to perform an offset measurement.



**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>timeInMs</i>	Time for offset measurement in ms.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.4.3.9 GOMDMSC15\_measurePulse()**

```
GODLL int GOFUNCDESC GOMDMSC15_measurePulse (
    int handle,
    double pulseTime,
    double samplingRate )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This method triggers a pulse measurement. A pulse measurement is very fast and individual measurements, with a pulse profile is recorded. The function returns only after the entire measurement is completed.

With the function dequeuePulse () the measurement times and radiometric values of the individual measurements can be read in a separate thread.

After the pulse measurement, the measured values for the individual measurement with the largest radiometric integral in the SDK are stored and can be queried using the functions in the chapter "Reading out the measured values"

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>pulseTime</i>	The duration of the pulse measurement in seconds
in	<i>samplingRate</i>	The sampling rate in Hz determines how quick succession, the individual measurements are to be held. If not enough signal is available, it may be that the adjusted sampling rate is not achieved, since the individual measurements duration is too long.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.4.3.10 GOMDMSC15\_dequeuePulse()

```
GODLL int GOFUNCDESC GOMDMSC15_dequeuePulse (
    int handle,
    double * timer,
    double * value )
```

##### Note

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This function reads the measurement time and radiometric values during or after a pulse measurement. It is thread-safe and can be accessed during pulse measurement in a separate thread to read the values of the current pulse measurement.

They should be called in a loop until all measurements have been collected. If the function return value -25030 (Errors), it means that no measurement values exist.

##### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>timer</i>	Measurement time of individual measurement.
out	<i>value</i>	Radiometric value of single measurement.

##### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.4.3.11 GOMDMSC15\_abortPulse()

```
GODLL int GOFUNCDESC GOMDMSC15_abortPulse (
    int handle )
```

##### Note

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This function cancels the current pulse measurement. It must be called in a separate thread and causes the GOMDMSC15\_measurePulse() function is terminated directly.

##### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	---------------	--

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to “0”.

## 5.5 Methods for spectral measurement settings

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_getLastIntegrationTime (int handle, double \*timeInS)
- GODLL int GOFUNCDESC GOMDMSC15\_getWLBorders (int handle, double \*startWL, double \*endWL)
- GODLL int GOFUNCDESC GOMDMSC15\_getWLMapping (int handle, double \*wavelengths)
- GODLL int GOFUNCDESC GOMDMSC15\_getSpectralDataByPixel (int handle, double \*spectrum)
- GODLL int GOFUNCDESC GOMDMSC15\_getSpectralData (int handle, double startWL, double deltaWL, int nrOfSteps, double \*spectrum)
- GODLL int GOFUNCDESC GOMDMSC15\_getPeakWL (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getCentreWL (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getCentroidWL (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getFWHM (int handle, double \*value)

### 5.5.1 Detailed Description

Methods to perform a spectral measurement.

### 5.5.2 C++ Example

Reads the spectrum in pixel steps (288) from MSC15-device.

```
int handle;
GOMDMSC15_getHandle(NULL, &handle);           //initialization of device
double spectrum[288];                          //Array for 288 pixel
GOMDMSC15_getSpectralData(handle, &spectrum);   //call spectrum
//Do something with data
GOMDMSC15_releaseHandle(handle);               //re-initialization of device
```

### 5.5.3 Function Documentation

#### 5.5.3.1 GOMDMSC15\_getLastIntegrationTime()

```
GODLL int GOFUNCDESC GOMDMSC15_getLastIntegrationTime (
    int handle,
    double * timeInS )
```

This function returns the measurement time (integration time) of the last measurement. Last measurement can be, among other things, its internal measurement of the device during initialization, GOMDMSC15\_measureDarkOffset(), GOMDMSC15\_measure(), ... . I.e. it is advisable to call this method directly after the measurement has been performed.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>timeInS</i>	Pointer to Double value; integration time in seconds

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.5.3.2 GOMDMSC15\_getWLBorders()**

```
GODLL int GOFUNCDESC GOMDMSC15_getWLBorders (
    int handle,
    double * startWL,
    double * endWL )
```

This function retrieves the wavelength limit of the device.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>startWL</i>	Pointer to Double value; wavelength start
out	<i>endWL</i>	Pointer to Double value; wavelength end

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.5.3.3 GOMDMSC15\_getWLMapping()**

```
GODLL int GOFUNCDESC GOMDMSC15_getWLMapping (
    int handle,
    double * wavelengths )
```

This function retrieves the wavelength points for the 288 pixels of the device.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>wavelengths</i>	Pointer to array of doubles; array with the wavelength bases. The array must be pre-initialized with a size of 288th

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.5.3.4 GOMDMSC15\_getSpectralDataByPixel()

```
GODLL int GOFUNCDESC GOMDMSC15_getSpectralDataByPixel (
    int handle,
    double * spectrum )
```

Determines the measured data and the calibration spectrum and outputs in pixel-based steps. GetWLMapping with the wavelengths can be accessed, which belong to the 288 pixels.

##### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>spectrum</i>	Pointer to the first element of a double array containing the calculated Readings. The size of the array must be set to the 288th.

##### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.5.3.5 GOMDMSC15\_getSpectralData()

```
GODLL int GOFUNCDESC GOMDMSC15_getSpectralData (
    int handle,
    double startWL,
    double deltaWL,
    int nrOfSteps,
    double * spectrum )
```

Determines the measured data and the calibration spectrum and outputs this in the specified range (start wavelength, increment and number of values). The spectrum is here interpolated to the desired range. With getWL↔ Borders the maximum limits can be read on the spectrum.

##### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>startWL</i>	Start wavelength.
in	<i>deltaWL</i>	Increment of wavelength between einzelnen values.
in	<i>nrOfSteps</i>	Number of output values. Thus, the end wavelength is also set automatically.
in	<i>spectrum</i>	Pointer to the first element of a double array containing the calculated Readings. The size of the array is defined with nrOfSteps.

##### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.5.3.6 GOMDMSC15\_getPeakWL()**

```
GODLL int GOFUNCDESC GOMDMSC15_getPeakWL (
    int handle,
    double * value )
```

Returns the wavelength at which the spectrum is maximum.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains the wavelength [nm].

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.5.3.7 GOMDMSC15\_getCentreWL()**

```
GODLL int GOFUNCDESC GOMDMSC15_getCentreWL (
    int handle,
    double * value )
```

Returns the center wave length.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains the center of the center wavelength in [nm].

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.5.3.8 GOMDMSC15\_getCentroidWL()**

```
GODLL int GOFUNCDESC GOMDMSC15_getCentroidWL (
    int handle,
    double * value )
```

Returns the centroid wavelength. The center wavelength is a measure to aspectrumto characterize. It indicates, where is the "center" of the spectrum.

**Parameters**

in	<i>handle</i>	Integer value $> 0$ for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains the centroid wavelength in [nm].

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to “0”.

**5.5.3.9 GOMDMSC15\_getFWHM()**

```
GODLL int GOFUNCDESC GOMDMSC15_getFWHM (
    int handle,
    double * value )
```

Returns the FWHM (full width at FDHM = half maximum) of the measured spectrum.

**Parameters**

in	<i>handle</i>	Integer value $> 0$ for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains half-width in [nm].

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to “0”.



## 5.6 Methods for integral measurement settings

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_getPhotopic (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getScotopic (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getSPRatio (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getRadiometricUnit (int handle, int \*unit)
- GODLL int GOFUNCDESC GOMDMSC15\_getRadiometricValue (int handle, double startWL, double endWL, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getPAR (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getBilirubinIEC (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getBilirubinAAP (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getBilirubinAAP2004 (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getBilirubinNatus (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getMelanopic (int handle, double \*Ev, double \*Eemel, double \*EvmelD65)

### 5.6.1 Detailed Description

Methods to perform a integral measurement.

### 5.6.2 C++ Example

Read the value PAR [ $\mu\text{mol}/\text{m}^2/\text{s}$ ] from the device.

```
int handle;
double value;
GOMDMSC15_getHandle(NULL, &handle);           //initialization of device
GOMDMSC15_measure();                           //start measure
GOMDMSC15_getPAR(handle, &value);              //call value
//Do something with data
GOMDMSC15_releaseHandle(handle);               //re-initialization of device
```

### 5.6.3 Function Documentation

#### 5.6.3.1 GOMDMSC15\_getPhotopic()

```
GODLL int GOFUNCDESC GOMDMSC15_getPhotopic (
    int handle,
    double * value )
```

Returns the value of the last measured photopic spectrum.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value to return contains the calculated photopic value

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.6.3.2 GOMDMSC15\_getScotopic()**

```
GODLL int GOFUNCDESC GOMDMSC15_getScotopic (
    int handle,
    double * value )
```

Returns the scotopic value of the last measured spectrum.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value to return contains the calculated photopic value.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.6.3.3 GOMDMSC15\_getSPRatio()**

```
GODLL int GOFUNCDESC GOMDMSC15_getSPRatio (
    int handle,
    double * value )
```

Returns the ratio of scotopischem and photopic value.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value to return containing scotopisch / photopic ratio.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.6.3.4 GOMDMSC15\_getRadiometricUnit()**

```
GODLL int GOFUNCDESC GOMDMSC15_getRadiometricUnit (
    int handle,
    int * unit )
```

This function shows the unity of the radiometric value.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>unit</i>	Pointer to an integer value: <ul style="list-style-type: none"> <li>• 0: 'W' (MSC15-W)</li> <li>• 1: 'W/m2'</li> </ul>

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.6.3.5 GOMDMSC15\_getRadiometricValue()

```
GODLL int GOFUNCDESC GOMDMSC15_getRadiometricValue (
    int handle,
    double startWL,
    double endWL,
    double * value )
```

This function returns the value of the radiometric integral.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>startWL</i>	Start value of the range in which the integral is to be calculated.
in	<i>endWL</i>	End value of the range in which the integral is to be calculated.
out	<i>value</i>	Pointer to Double value: Radiometric integral in the specified wavelength range

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.6.3.6 GOMDMSC15\_getPAR()

```
GODLL int GOFUNCDESC GOMDMSC15_getPAR (
    int handle,
    double * value )
```

This method returns the value of PAR in mol / m2 / s.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains the measured value of PAR.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.6.3.7 GOMDMSC15\_getBilirubinIEC()**

```
GODLL int GOFUNCDESC GOMDMSC15_getBilirubinIEC (
    int handle,
    double * value )
```

This method returns the value of bilirubin according to IEC 60601-2-50.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains a value of bilirubin according to IEC 60601-2-50.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.6.3.8 GOMDMSC15\_getBilirubinAAP()**

```
GODLL int GOFUNCDESC GOMDMSC15_getBilirubinAAP (
    int handle,
    double * value )
```

This method returns the value of bilirubin by the AAP (American Academy of Pediatrics) of 2011.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains a value of bilirubin by AAP.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to “0”.

**5.6.3.9 GOMDMSC15\_getBilirubinAAP2004()**

```
GODLL int GOFUNCDESC GOMDMSC15_getBilirubinAAP2004 (
    int handle,
    double * value )
```

This method returns the value of bilirubin by the AAP (American Academy of Pediatrics).

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains a value of bilirubin by AAP of 2004.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to “0”.

**5.6.3.10 GOMDMSC15\_getBilirubinNatus()**

```
GODLL int GOFUNCDESC GOMDMSC15_getBilirubinNatus (
    int handle,
    double * value )
```

This method returns the value of bilirubin claimed by Natus of a blue LED.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains a value of bilirubin of a blue LED.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to “0”.

**5.6.3.11 GOMDMSC15\_getMelanopic()**

```
GODLL int GOFUNCDESC GOMDMSC15_getMelanopic (
    int handle,
```

```
double * Ev,  
double * Eemel,  
double * EvmelD65 )
```

This method returns melanopic values.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>Ev</i>	Pointer to Double value, illuminance
out	<i>Eemel</i>	Pointer to Double value, melanopic irradiance
out	<i>EvmelD65</i>	Pointer to Double value, daylight-equivalent(D65) melanopic illuminance

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

## 5.7 Methods for color measurement

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_getColor (int handle, double \*XValue, double \*YValue, double \*ZValue)
- GODLL int GOFUNCDESC GOMDMSC15\_getColorCIE1931 (int handle, double \*xValue, double \*yValue)
- GODLL int GOFUNCDESC GOMDMSC15\_getColorCIE1976 (int handle, double \*uValue, double \*vValue)
- GODLL int GOFUNCDESC GOMDMSC15\_getCRI (int handle, double \*values)
- GODLL int GOFUNCDESC GOMDMSC15\_getCCT (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getDomWL (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getCompWL (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getDeltauv (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getPurity (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_getTM3018 (int handle, double \*Rf, double \*Rg)
- GODLL int GOFUNCDESC GOMDMSC15\_getTM3018RfByHue (int handle, double \*values)

### 5.7.1 Detailed Description

Methods to perform a color measurement.

### 5.7.2 C++ Example

Read u' and v' (CIE1976) from the device.

```
int handle;
GOMDMSC15_getHandle(NULL, &handle);           //initialization of device
GOMDMSC15_measure();                           //start measure
double u, v;
GOMDMSC15_getColorCIE1976(handle, &u, &v);    //call value u, v
//Do something with data
GOMDMSC15_releaseHandle(handle);               //re-initialization of device
```

### 5.7.3 Function Documentation

#### 5.7.3.1 GOMDMSC15\_getColor()

```
GODLL int GOFUNCDESC GOMDMSC15_getColor (
    int handle,
    double * XValue,
    double * YValue,
    double * ZValue )
```

This method returns all the calculated color values based on a spectral measurement. The spectral and color calculation must have been activated prior to the measurement.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>XValue</i>	Pointer to Double value contains "large" X.
out	<i>YValue</i>	Pointer to Double value contains "large" Y.
out	<i>ZValue</i>	Pointer to Double value contains "large" Z.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.2 GOMDMSC15\_getColorCIE1931()**

```
GODLL int GOFUNCDESC GOMDMSC15_getColorCIE1931 (
    int handle,
    double * xValue,
    double * yValue )
```

This method returns the x and y color coordinates of the CIE1931 color space.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>xValue</i>	Pointer to Double value contains, x corresponding to the color space CIE1931.
out	<i>yValue</i>	Pointer to Double value, y contains the corresponding CIE1931 color space.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.3 GOMDMSC15\_getColorCIE1976()**

```
GODLL int GOFUNCDESC GOMDMSC15_getColorCIE1976 (
    int handle,
    double * uValue,
    double * vValue )
```

This method returns the u 'and v' color coordinates of CIE1976 color space.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>uValue</i>	Pointer to Double value contains, u 'corresponding to the color space CIE1976
out	<i>vValue</i>	Pointer to Double value contains, v 'corresponding to the color space CIE1976

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".



### 5.7.3.4 GOMDMSC15\_getCRI()

```
GODLL int GOFUNCDESC GOMDMSC15_getCRI (
    int handle,
    double * values )
```

Under color rendering index (English Colour Rendering Index, CRI) is defined as a photometric Size, with the quality of Color rendering from light sources the same correlated color temperature can be described. As a reference to evaluate the reproduction quality is used up to a color temperature of 5000 K, the light from a black body the corresponding color temperature is discharged. About 5000 K is referenced against a daylight-like spectral distribution. For example, the color reproduction of a household light bulb for the calculation (which is itself a good approximation a black body is) the spectrum of a black body with a temperature of 2700 K is used as a reference for a fluorescent lamp with the light color 865 (865 for a color rendering index of more than 80, 865 for a color temperature of 6500 K), however, the spectrum of daylight illuminant D65. The color rendering index is by definition a special metamerism, To calculate the color rendering index are 14 test colors with a standardized Reflectance curve defined. Mismatch of the spectra between reference and test range is used as a measure for the 14 special color rendering indices. To calculate the general color rendering index Ra, however, only the first eight test colors are used. The 14 test colors are selected by DIN 6169th Here, the color rendering index Ri for color can be found i. A numerical measure of the colors # 1 to # 8 is denoted by Ra. As in the definition of the color rendering index in the 1930s, the reference light sources 100, the then current fluorescent lamps (sort of arbitrarily) were set at 50 and the color rendering index is by no means a percentage value, and negative color rendering indices are possible.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>values</i>	Pointer to the first element of a double array. This contains the calculated CRI values after return. The size of the array must be initialized by 16. values[0] then contains the Ra value. The entries values[1] - values[15] contain the values R1 - R15.

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

### 5.7.3.5 GOMDMSC15\_getCCT()

```
GODLL int GOFUNCDESC GOMDMSC15_getCCT (
    int handle,
    double * value )
```

Returns the last measurement, the color temperature (CCT).

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value to return the CCT determined contains value

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.6 GOMDMSC15\_getDomWL()**

```
GODLL int GOFUNCDESC GOMDMSC15_getDomWL (
    int handle,
    double * value )
```

Returns the dominant wavelength of the last measurement.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value to return contains the calculated value of the dominant wavelength

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.7 GOMDMSC15\_getCompWL()**

```
GODLL int GOFUNCDESC GOMDMSC15_getCompWL (
    int handle,
    double * value )
```

Returns the complementary wavelength of the last measurement.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value to return contains the calculated value of the complementary wavelength

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.8 GOMDMSC15\_getDeltauv()**

```
GODLL int GOFUNCDESC GOMDMSC15_getDeltauv (
    int handle,
    double * value )
```

Returns the actually existing at the last measurement delta uv value.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value, the delta contains determined to return value uv

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.9 GOMDMSC15\_getPurity()**

```
GODLL int GOFUNCDESC GOMDMSC15_getPurity (
    int handle,
    double * value )
```

Provides color purity Latter measurement.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to Double value that contains the color purity

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.10 GOMDMSC15\_getTM3018()**

```
GODLL int GOFUNCDESC GOMDMSC15_getTM3018 (
    int handle,
    double * Rf,
    double * Rg )
```

**TM-30-18** is a color rendering index published by the IES. Unlike the CRI it is based on 99 different test colors in order to obtain an accurate and adapted to all types of light rating system. The main indicators in TM-30-18, the values Rf (Fidelity Index) and Rg (Gamut Index). Rf is basically comparable to the Ra value of the CRI. The Rg value is in addition to the saturation of the colors under the measured light.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>Rf</i>	Pointer to Double value: Fidelity Index
out	<i>Rg</i>	Pointer to Double value: Gammoth Index

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.7.3.11 GOMDMSC15\_getTM3018RfByHue()**

```
GODLL int GOFUNCDESC GOMDMSC15_getTM3018RfByHue (
    int handle,
    double * values )
```

When CRI there are the values of R1-R15. In order to give a statement about the color quality for each color when TM-30-15 there is the splitting of the Rf in 16 average color rendering values. The Rf [by Hue].

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>values</i>	Pointer to the first element of a double array. This contains the calculated Rf values by color. The size of the array must be vorinialisiert by 16.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

## 5.8 Load stored Measurements from Device

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_loggerReadDate (int handle, int index, char \*date)
- GODLL int GOFUNCDESC GOMDMSC15\_loggerLoadMeasurement (int handle, int index)
- GODLL int GOFUNCDESC GOMDMSC15\_loggerDeleteMeasurement (int handle, int index)
- GODLL int GOFUNCDESC GOMDMSC15\_loggerSetRTC (int handle, char \*date)
- GODLL int GOFUNCDESC GOMDMSC15\_loggerGetRTC (int handle, char \*date)

### 5.8.1 Detailed Description

Methods to read, load and delete measurements from the internal device logger.

Saving of measurement data is only possible in handheld mode.

### 5.8.2 Function Documentation

#### 5.8.2.1 GOMDMSC15\_loggerReadDate()

```
GODLL int GOFUNCDESC GOMDMSC15_loggerReadDate (
    int handle,
    int index,
    char * date )
```

#### Note

This function can be used with the following device types: **MSC15, MSC15-Bili, CSS-45, CSS-45-HI, CSS-45-WT, CSS-45 + CSS-D**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This methods read the date of a measurement saved in the internal data logger.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	index of measurement in internal data logger (0-9)
out	<i>date</i>	Null-terminated string; contains by return the date and time(TTMMJJhhmmss)

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

### 5.8.2.2 GOMDMSC15\_loggerLoadMeasurement()

```
GODLL int GOFUNCDESC GOMDMSC15_loggerLoadMeasurement (
    int handle,
    int index )
```

#### Note

This function can be used with the following device types: **MSC15, MSC15-Bili, CSS-45, CSS-45-HI, CSS-45-WT, CSS-45 + CSS-D**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This methods loads a measurement from the internal data logger. To get the data you can use the common routines for reading measurement data. Actual Measurement values will be overwritten by calling this method.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	index of measurement in internal data logger (0-9)

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

### 5.8.2.3 GOMDMSC15\_loggerDeleteMeasurement()

```
GODLL int GOFUNCDESC GOMDMSC15_loggerDeleteMeasurement (
    int handle,
    int index )
```

#### Note

This function can be used with the following device types: **MSC15, MSC15-Bili, CSS-45, CSS-45-HI, CSS-45-WT, CSS-45 + CSS-D**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This methods deletes the measurement at given index from the internal data logger.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	index of measurement in internal data logger (0-9)

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.8.2.4 GOMDMSC15\_loggerSetRTC()**

```
GODLL int GOFUNCDESC GOMDMSC15_loggerSetRTC (
    int handle,
    char * date )
```

**Note**

This function can be used with the following device types: **MSC15, MSC15-Bili, CSS-D**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This methods sets the internal Real Time Clock of the device. This clock is used for the device logger

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>date</i>	Null-terminated string; containing the date and time(TTMMJJhhmmss)

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.8.2.5 GOMDMSC15\_loggerGetRTC()**

```
GODLL int GOFUNCDESC GOMDMSC15_loggerGetRTC (
    int handle,
    char * date )
```

**Note**

This function can be used with the following device types: **MSC15, MSC15-Bili, CSS-D**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

This method reads the internal Real Time Clock of the device. This clock is used for the device logger.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>date</i>	Null-terminated string; contains by return the date and time(TTMMJJhhmmss)

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".



## 5.9 Methods only for MSC15-W-devices

### Functions

- GODLL int GOFUNCDESC GOMDMSC15\_setUserWLRangeBorders (int handle, int userRange, double startWL, double endWL)
- GODLL int GOFUNCDESC GOMDMSC15\_setUserWLRangeBoarders (int handle, int userRange, double startWL, double endWL)
- GODLL int GOFUNCDESC GOMDMSC15\_setUserWLRangeBordersToFactory (int handle)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserWLRangeBorders (int handle, int userRange, double \*startWL, double \*endWL)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserWLRangeBoarders (int handle, int userRange, double \*startWL, double \*endWL)
- GODLL int GOFUNCDESC GOMDMSC15\_getSelectedUserWLRange (int handle, int \*userRange, bool \*locked)
- GODLL int GOFUNCDESC GOMDMSC15\_setSelectedUserWLRange (int handle, int userRange, bool locked)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserWLRangeActive (int handle, int userRange, bool \*active)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserWLRangeModifiable (int handle, int userRange, bool \*modifiable)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserWLRangeRadiometric (int handle, int userRange, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_setApertureSize (int handle, int index, double size)
- GODLL int GOFUNCDESC GOMDMSC15\_getApertureSize (int handle, int index, double \*size)
- GODLL int GOFUNCDESC GOMDMSC15\_getApertureSizeBorders (int handle, double \*minSize, double \*maxSize)
- GODLL int GOFUNCDESC GOMDMSC15\_setApertureIndex (int handle, int index)
- GODLL int GOFUNCDESC GOMDMSC15\_getApertureIndex (int handle, int \*index)
- GODLL int GOFUNCDESC GOMDMSC15\_setUserCorrectionFactor (int handle, double value)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserCorrectionFactor (int handle, double \*value)
- GODLL int GOFUNCDESC GOMDMSC15\_setUserCorrectionFactorLocked (int handle, bool value)
- GODLL int GOFUNCDESC GOMDMSC15\_getUserCorrectionFactorLocked (int handle, bool \*value)

### 5.9.1 Detailed Description

These methods can only be used in combination with an MSC15-W-device.

### 5.9.2 Function Documentation

#### 5.9.2.1 GOMDMSC15\_setUserWLRangeBorders()

```
GODLL int GOFUNCDESC GOMDMSC15_setUserWLRangeBorders (
    int handle,
    int userRange,
    double startWL,
    double endWL )
```

#### Note

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Sets the wavelength limits for user adjustable wavelength ranges.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>userRange</i>	Integer value; the wavelength range for which the limits are to be set. (range 0-7)
in	<i>startWL</i>	Double value; start wavelength for the range
in	<i>endWL</i>	Double value; end of the shaft length limit

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.2 GOMDMSC15\_setUserWavelengthRangeBorders()**

```
GODLL int GOFUNCDESC GOMDMSC15_setUserWavelengthRangeBorders (
    int handle,
    int userRange,
    double startWL,
    double endWL )
```

**5.9.2.3 GOMDMSC15\_setUserWavelengthRangeBordersToFactory()**

```
GODLL int GOFUNCDESC GOMDMSC15_setUserWavelengthRangeBordersToFactory (
    int handle )
```

**Note**

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Sets the wavelength limits for user adjustable wavelength ranges back to factory settings.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
----	---------------	--

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.9.2.4 GOMDMSC15\_getUserWLRangeBorders()

```
GODLL int GOFUNCDESC GOMDMSC15_getUserWLRangeBorders (
    int handle,
    int userRange,
    double * startWL,
    double * endWL )
```

##### Note

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Reads the wavelength limits for user adjustable wavelength ranges.

##### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>userRange</i>	Integer value, the wavelength range for which the limits are to be read (range 0-7)
in	<i>startWL</i>	Pointer to double value, start wavelength for the range
in	<i>endWL</i>	Pointer to double value, end of the shaft length limit

##### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

#### 5.9.2.5 GOMDMSC15\_getUserWLRangeBoards()

```
GODLL int GOFUNCDESC GOMDMSC15_getUserWLRangeBoards (
    int handle,
    int userRange,
    double * startWL,
    double * endWL )
```

#### 5.9.2.6 GOMDMSC15\_getSelectedUserWLRange()

```
GODLL int GOFUNCDESC GOMDMSC15_getSelectedUserWLRange (
    int handle,
    int * userRange,
    bool * locked )
```

##### Note

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Gets the wavelength range from MSC15-device, which is currently used on the device display.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>userRange</i>	Pointer to integer value, the wavelength range which is currently set. (There are the areas 0-7)
out	<i>locked</i>	Pointer to boolean value: <ul style="list-style-type: none"> <li>• true: Area is locked</li> <li>• false Area is not locked</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.7 GOMDMSC15\_setSelectedUserWLRange()**

```
GODLL int GOFUNCDESC GOMDMSC15_setSelectedUserWLRange (
    int handle,
    int userRange,
    bool locked )
```

**Note**

This function can be used with the following device types: **MSC15-W**  
The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Sets the wavelength range, which is used on the device display.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>userRange</i>	Integer value; the wavelength range for which the limits are to be read (range 0-7)
in	<i>locked</i>	Boolean value; this area is to be locked in the unit. Can not then be changed by the user.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.8 GOMDMSC15\_getUserWLRangeActive()**

```
GODLL int GOFUNCDESC GOMDMSC15_getUserWLRangeActive (
    int handle,
    int userRange,
    bool * active )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function `GOMDMSC15_getMSC15DeviceType()`.

Retrieves whether a wavelength range is active, and can thus be selected by the user in the device. This value is set by Gigahertz-Optik when the device is shipped.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the <code>getHandle</code> method.
in	<i>userRange</i>	Integer value; the wavelength range for which the limits are to be read (range 0-7)
out	<i>active</i>	Pointer to boolean value: <ul style="list-style-type: none"> <li>• true: Range is active</li> <li>• false: Range is not active</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.9 GOMDMSC15\_getUserWLRRangeModifiable()**

```
GODLL int GOFUNCDESC GOMDMSC15_getUserWLRRangeModifiable (
    int handle,
    int userRange,
    bool * modifiable )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function `GOMDMSC15_getMSC15DeviceType()`.

Retrieves whether a wavelength range is modifiable, and can thus be changed by the user in the device. This value is set by Gigahertz-Optik when the device is shipped.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the <code>getHandle</code> method.
in	<i>userRange</i>	Integer value; the wavelength range for which the limits are to be read (range 0-7)
out	<i>modifiable</i>	Pointer to boolean value: <ul style="list-style-type: none"> <li>• true: Range is modifiable</li> <li>• false: Range is not modifiable</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.10 GOMDMSC15\_getUserWLRRangeRadiometric()**

```
GODLL int GOFUNCDESC GOMDMSC15_getUserWLRRangeRadiometric (
    int handle,
    int userRange,
    double * value )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Calculates the radiometric value of the spectrum in the wavelength limits that have been set with GOMDMSC15\_setUserWLRRangeBoards().

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>userRange</i>	Integer value; the wavelength range for which the limits are to be read (range 0-7)
out	<i>value</i>	Pointer to double value; radiometric value in the range of wavelength limits.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.11 GOMDMSC15\_setApertureSize()**

```
GODLL int GOFUNCDESC GOMDMSC15_setApertureSize (
    int handle,
    int index,
    double size )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Sets the aperture diameter for the MSC15-W. Up to 5 diameters are stored in the device. With GOMDMSC15\_setApertureIndex() a aperture can be selected. Caution: The aperture diameter is not automatically charged the SDK functions. If you want to determine the irradiance, you must perform the calculation itself.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	Integer value; the aperture index, which is to be changed. (possible values are 0-4)
in	<i>size</i>	Double value; value of the aperture diameter

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.12 GOMDMSC15\_getAppertureSize()**

```
GODLL int GOFUNCDESC GOMDMSC15_getAppertureSize (
    int handle,
    int index,
    double * size )
```

**Note**

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Reads the aperture diameter for a particular index.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	Integer value, the aperture index, which is to be changed. (possible values are 0-4)
out	<i>size</i>	Pointer to double value, value of the aperture diameter.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.13 GOMDMSC15\_getAppertureSizeBorders()**

```
GODLL int GOFUNCDESC GOMDMSC15_getAppertureSizeBorders (
    int handle,
    double * minSize,
    double * maxSize )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Reads the input limits, which can be used for setAppertureSize. These have been defined by Gigahertz-Optik.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>minSize</i>	Pointer to double value, minimum value of the aperture diameter.
out	<i>maxSize</i>	Pointer to double value, maximum value of the aperture diameter.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.14 GOMDMSC15\_setAppertureIndex()**

```
GODLL int GOFUNCDESC GOMDMSC15_setAppertureIndex (
    int handle,
    int index )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Defines the aperture diameter (index) to be used in the device for clearing. Caution: The aperture diameter is not automatically charged the SDK functions. If you want to determine the irradiance, you must perform the calculation itself.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	Integer value, the aperture index, which is to be set to active. (possible values 0-4)

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".



### 5.9.2.15 GOMDMSC15\_getAppertureIndex()

```
GODLL int GOFUNCDESC GOMDMSC15_getAppertureIndex (
    int handle,
    int * index )
```

#### Note

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Sets the Apperturgröße for MSC15-W. Up to 5 Apperturgrößen be stored in the device. With GOMDMSC15\_setAppertureIndex() a Apperur can be selected.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>index</i>	Integer value, the aperture index, which is actually active. (possible values 0-4)

#### Returns

Integer values; see return value table (warnings and errors) for values unequal to "0".

### 5.9.2.16 GOMDMSC15\_setUserCorrectionFactor()

```
GODLL int GOFUNCDESC GOMDMSC15_setUserCorrectionFactor (
    int handle,
    double value )
```

#### Note

This function can be used with the following device types: **MSC15-W**  
 The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Sets the user settable correction factor. Note: The correction factor is automatically charged to the spectrum and all derived metrics. The accuracy of the values accepts Gigahertz-Optik no guarantee.

#### Parameters

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
in	<i>value</i>	Double value, the desired correction factor.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.17 GOMDMSC15\_getUserCorrectionFactor()**

```
GODLL int GOFUNCDESC GOMDMSC15_getUserCorrectionFactor (
    int handle,
    double * value )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Reads out the adjusted correction factor. Note: The correction factor is automatically charged to the spectrum and all derived metrics. The accuracy of the values accepts Gigahertz-Optik no guarantee.

**Parameters**

in	<i>handle</i>	Integer value > 0 for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to double value, returns the current correction factor.

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.18 GOMDMSC15\_setUserCorrectionFactorLocked()**

```
GODLL int GOFUNCDESC GOMDMSC15_setUserCorrectionFactorLocked (
    int handle,
    bool value )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Locks the currently set correction factor in the device. This cannot be changed then the device display from the user.

**Note:** The correction factor is automatically charged to the spectrum and all derived metrics. The accuracy of the values accepts Gigahertz-Optik no guarantee.

**Parameters**

in	<i>handle</i>	Integer value $> 0$ for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Boolean value: <ul style="list-style-type: none"> <li>• true: Value is locked</li> <li>• false: Value can be changed</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".

**5.9.2.19 GOMDMSC15\_getUserCorrectionFactorLocked()**

```
GODLL int GOFUNCDESC GOMDMSC15_getUserCorrectionFactorLocked (
    int handle,
    bool * value )
```

**Note**

This function can be used with the following device types: **MSC15-W**

The device type can be determined with the function GOMDMSC15\_getMSC15DeviceType().

Determines whether the currently set for the machine correction factor is locked. Note: The correction factor is automatically charged to the spectrum and all derived metrics. The accuracy of the values accepts Gigahertz-Optik no guarantee.

**Parameters**

in	<i>handle</i>	Integer value $> 0$ for unique identification of the instantiated MSC15 and CSS device type; this value is returned by the getHandle method.
out	<i>value</i>	Pointer to boolean value: <ul style="list-style-type: none"> <li>• true: Value is locked</li> <li>• false: Value can be changed</li> </ul>

**Returns**

Integer values; see return value table (warnings and errors) for values unequal to "0".